Regression analysis Two variables

(Montgomery and Runger: ch 11 Brani Vidakovic: ch 14)

Reminder

Covariance Defined

Covariance is a number qunatifying average dependence between two random variables.

The covariance between the random variables X and Y, denoted as cov(X,Y) or σ_{XY} is

$$\sigma_{XY} = E\left[\left(X - \mu_X\right)\left(Y - \mu_Y\right)\right] = E\left(XY\right) - \mu_X\mu_Y \tag{5-14}$$

The units of σ_{yy} are units of X times units of Y.

Unlike the range of variance, $-\infty < \sigma_{XY} < \infty$.

Correlation is "normalized covariance"

Also called:

Pearson correlation coefficient

 $\rho_{XY} = \sigma_{XY} / \sigma_X \sigma_Y$ is the covariance normalized to be $-1 \le \rho_{XY} \le 1$



Karl Pearson (1852–1936) English mathematician and biostatistician

Covariance and Scatter Patterns





Figure 5-13 Joint probability distributions and the sign of cov(X, Y). Note that covariance is a measure of linear relationship. Variables with non-zero covariance are correlated.

Regression analysis

- Many problems in engineering and science involve sample in which two or more variables were measured. They may not be independent from each other and one (or several) of them can be used to predict another
- Everyday example: in most samples height and weight of people are related to each other
- Biological example: in a cell sorting experiment the copy number of a protein may be measured alongside its volume
- Regression analysis uses a sample to build a model to predict protein copy number given a cell volume




Sir Francis Galton, (1822 -1911) was an English statistician, anthropologist, proto-geneticist, psychometrician, eugenicist, ("Nature vs Nurture", inheritance of intelligence), tropical explorer, geographer, inventor (Galton Whistle to test hearing), meteorologist (weather map, anticyclone).

Invented both correlation and regression analysis when studied heights of fathers and sons

Found that fathers with height above average tend to have sons with height also above average but closer to the average. Hence "regression" to the mean

Two variable samples



- Oxygen can be distilled from the air
- Hydrocarbons need to be filtered out or the whole thing would go kaboom!!!
- When more hydrocarbons were removed, the remaining oxygen stays cleaner
- Except we don't know how dirty was the air to begin with

Table 11-1 Oxygen and Hydrocarbon Levels

Observation Number	Hydrocarbon Level $x(\%)$	Purity y(%)
1	0.99	90.01
2	1.02	89.05
3	1.15	91.43
4	1.29	93.74
5	1.46	96.73
6	1.36	94.45
7	0.87	87.59
8	1.23	91.77
9	1.55	99.42
10	1.40	93.65
11	1.19	93.54
12	1.15	92.52
13	0.98	90.56
14	1.01	89.54
15	1.11	89.85
16	1.20	90.39
17	1.26	93.25
18	1.32	93.41
19	1.43	94.98
20	0.95	87.33

$$Y = \beta_0 + \beta_1 \times + \epsilon$$




Figure 11-1 Scatter diagram of oxygen purity versus hydrocarbon level from Table 11-1.

Linear regression

The simple linear regression model is given by

$$Y = \beta_0 + \beta_1 X + E = \hat{Y} + E$$

E is the random error

slope β_1 and intercept β_0 of the line are called regression coefficients

Note: Y, \hat{Y} , X and E are random variables

Let's assume that
$$E(E|x)=0 \rightarrow E(Y|x) = \beta_0 + \beta_1 x + E(E|x) = \beta_0 + \beta_1 x$$

Y=
$$\beta_0 + \beta_1 \times + \epsilon$$
; $E(\epsilon|x) = 0$ $\forall x$
How does one find $\beta_0 + \beta_1 = 0$.
 $Cov(Y,X) = Cov((\beta_0 + \beta_1 \times + \epsilon), X) = 0$
 $E(x,X) = Cov(X,X) + Cov(X,X) + Cov(X,X)$
 $E(x,X) = 0$ Since $\beta_0 = 0$ Since $\beta_0 = 0$ Cov $(x,x) = E(x^2) - E(x)^2 = Var(X)$
 $E(x,X) = E(x^2) - E(x) = E(x) = 0$
 $E(x,X) = E(x,X) - E(x) = 0$
 $E(x,X) = E(x,X) = E(x,X)$
 $E(x,X) = E(x,X) = E(x,X)$
 $E(x,X) = E(x,X) = E(x,X)$
 $E(x,X) = E(x,X) = E(x,X)$

Method of least squares

• The method of least squares is used to estimate the parameters, β_0 and β_1 by minimizing the sum of the squares of the vertical deviations in Figure 11-3.

Figure 11-3 Deviations of the data from the estimated regression model.




Figure 11-3 Deviations of the data from the estimated regression model.

$$y_i = \beta_0 + \beta_1 x_i + \epsilon_i, \qquad i = 1, 2, ..., n$$
 (11-3)

and the sum of the squares of the deviations of the observations from the true regression line is

$$L = \sum_{i=1}^{n} \epsilon_i^2 = \sum_{i=1}^{n} (y_i - \beta_0 - \beta_1 x_i)^2$$
 (11-4)

The least squares estimators of β_0 and β_1 , say, $\hat{\beta}_0$ and $\hat{\beta}_1$, must satisfy

$$\frac{\partial L}{\partial \beta_{0}}\Big|_{\hat{\beta}_{0},\hat{\beta}_{1}} = -2\sum_{i=1}^{n} (y_{i} - \hat{\beta}_{0} - \hat{\beta}_{1}x_{i}) = 0$$

$$\frac{\partial L}{\partial \beta_{1}}\Big|_{\hat{\beta}_{0},\hat{\beta}_{1}} = -2\sum_{i=1}^{n} (y_{i} - \hat{\beta}_{0} - \hat{\beta}_{1}x_{i})x_{i} = 0$$

$$\hat{\beta}_{0} + \hat{\beta}_{1} \sum_{i=1}^{n} x_{i} = \sum_{i=1}^{n} y_{i}$$

$$\hat{\beta}_{0} \sum_{i=1}^{n} x_{i} + \hat{\beta}_{1} \sum_{i=1}^{n} x_{i}^{2} = \sum_{i=1}^{n} y_{i}x_{i}$$

$$(11-5)$$

$$\hat{\beta}_{0} \sum_{i=1}^{n} x_{i} + \hat{\beta}_{1} \sum_{i=1}^{n} x_{i}^{2} = \sum_{i=1}^{n} y_{i}x_{i}$$

$$(11-6) + \sum \hat{\beta}_{i} \sum_{i=1}^{n} \hat{\beta}_{i}$$

Traditional notation

Definition

The **least squares estimates** of the intercept and slope in the simple linear regression model are

$$\hat{\beta}_0 = \overline{y} - \hat{\beta}_1 \overline{x} \tag{11-7}$$

$$\hat{\beta}_{1} = \frac{\sum_{i=1}^{n} y_{i} x_{i} - \frac{\left(\sum_{i=1}^{n} y_{i}\right) \left(\sum_{i=1}^{n} x_{i}\right)}{n}}{\sum_{i=1}^{n} x_{i}^{2} - \frac{\left(\sum_{i=1}^{n} x_{i}\right)^{2}}{n}} = \frac{\sum_{i=1}^{n} y_{i} x_{i}}{\sum_{i=1}^{n} x_{i}} = \frac{\sum_{i=1}^{n} y_{i}}{\sum_{i=1}^{n} x_{i}} = \frac{\sum_{i=1}^{n}$$

where $\overline{y} = (1/n) \sum_{i=1}^{n} y_i$ and $\overline{x} = (1/n) \sum_{i=1}^{n} x_i$.

11-2: Simple Linear Regression

Definition

The **least squares estimates** of the intercept and slope in the simple linear regression model are

$$\hat{\beta}_{0} = \overline{y} - \hat{\beta}_{1}\overline{x}$$

$$\hat{\beta}_{1} = \frac{\sum_{i=1}^{n} y_{i} x_{i}}{\sum_{i=1}^{n} y_{i}} - \frac{\left(\sum_{i=1}^{n} y_{i}\right) \left(\sum_{i=1}^{n} x_{i}\right)}{n^{2}} = \frac{Cov\left(X, Y\right)}{\sqrt{qv\left(X\right)}}$$

$$\sum_{i=1}^{n} x_{i}^{2} - \frac{\left(\sum_{i=1}^{n} x_{i}\right)^{2}}{n^{2}} = \frac{Vqv\left(X\right)}{\sqrt{qv\left(X\right)}}$$
(11-8)

where $\overline{y} = (1/n) \sum_{i=1}^{n} y_i$ and $\overline{x} = (1/n) \sum_{i=1}^{n} x_i$.

11-4.2 Analysis of Variance Approach to Test Significance of Regression

The analysis of variance identity is

$$\sum_{i=1}^{n} (y_i - \bar{y})^2 = \sum_{i=1}^{n} (\hat{y}_i - \bar{y})^2 + \sum_{i=1}^{n} (y_i - \hat{y}_i)^2$$
 (11-24)

Symbolically,

$$SS_T = SS_R + SS_E \tag{11-25}$$

11-7: Adequacy of the Regression Model

11-7.2 Coefficient of Determination (R²) <u>VERY COMMONLY USED</u>

The quantity

$$R^2 = \frac{SS_R}{SS_T} = 1 - \frac{SS_E}{SS_T}$$

is called the **coefficient of determination** and is often used to judge the adequacy of a regression model.

- $0 \le R^2 \le 1$;
- We often refer (loosely) to R² as the amount of variability in the data explained or accounted for by the regression model.

Adjusted R-Squared

• Adjusted R-Squared uses unbiased estimates of σ_{ε}^2 and σ_{Y}^2 :

$$= 1 - \frac{\sigma_{\varepsilon}^{2}}{s_{Y}^{2}} = 1 - \frac{\frac{SS_{E}}{n-2}}{\frac{SS_{T}}{n-1}}$$

• For small samples it is different from the regular R-Squared: $R^2 = 1 - \frac{SS_E}{SS_m}$

11-7: Adequacy of the Regression Model

11-7.2 Coefficient of Determination (R²)

• For the oxygen purity regression model,

$$R^2 = SS_R/SS_T$$

= 152.13/173.38
= 0.877

• Thus, the model accounts for 87.7% of the variability in the data.

11-2: Simple Linear Regression

Estimating $\sigma_{\underline{\epsilon}}^2$

An unbiased estimator of σ_{ϵ}^{2} is

$$\hat{\mathbf{g}}^2 = \frac{SS_E}{n-2} \tag{11-13}$$

where SS_E can be easily computed using

$$SS_E = SS_T - \hat{\beta}_1 S_{xy} \tag{11-14}$$

11-3: Properties of the Least Squares Estimators

Slope Properties

$$E(\hat{\beta}_1) = \beta_1$$

• Intercept Properties

$$V(\hat{\beta}_1) = \frac{\sigma_{\epsilon}^2}{S_{xx}} = \frac{\delta_{\epsilon}^2}{n \delta_{\epsilon}^2}$$

$$Large \quad n \rightarrow Small \quad Variance \quad of \quad R_1$$

$$E(\hat{\beta}_0) = \beta_0 \quad \text{and} \quad V(\hat{\beta}_0) = \hat{\sigma}_2^2 \left[\frac{1}{n} + \frac{\overline{x}^2}{S_{xx}} \right] =$$

$$= \hat{\delta}_2^2 \left[1 + \frac{\mu_{\lambda}^2}{\delta_x^2} \right]^{\lambda} \frac{1}{h}$$




Figure 11-5 The null hypothesis H_0 : $\beta_1 = 0$ is accepted.




Figure 11-6 The null hypothesis H_0 : $\beta_1 = 0$ is rejected.

11-4.1 Use of Z-tests for large n

An important special case of the hypotheses of Equation 11-18 is

$$H_0: \beta_1 = 0$$

$$H_1: \beta_1 \neq 0$$

These hypotheses relate to the **significance of regression**. *Failure* to reject H_0 is equivalent to concluding that there is no linear relationship between X and Y.

$$H_0: \beta_1 = 0$$

$$H_1: \beta_1 \neq 0$$

$$\frac{1}{2} = \frac{\beta_1}{\beta_6}$$

$$\frac{3}{5} = \frac{1}{5}$$

Choose d (e.g. d=5%) for 95% confidence (n rejecting Ho)

$$Reject H_0 - \{ Z \} > Z_{2}^{=1.96}$$

11-4.1 Use of *t*-tests for smaller n.

The number of degrees of freedom in **n-2**

One can always fit a straight line through two points so one needs n>=3

$$H_0: \beta_1 = 0 \qquad \text{Choose d}$$

$$H_1: \beta_1 \neq 0 \qquad \text{(e.g. d=3\%)}$$

$$Confidence}$$

$$\text{(n rejecting)}$$

$$H_0) \hat{\beta}_{\delta} \qquad \text{(n rejecting)}$$

$$\frac{\beta_{\delta}}{\beta_{\delta}} \qquad \text{(n rejecting)}$$

$$\frac{\beta_{\delta}}{\beta_{\delta}} \qquad \text{(n rejecting)}$$

$$Reject H_0 - \mathcal{A} = t cdf(t_{\delta} \chi_1 + 2)^{\frac{1}{2}}$$

$$Reject H_0 - \mathcal{A} = t cdf(t_{\delta} \chi_1 + 2)^{\frac{1}{2}}$$

