


# Operating Systems Design (CS 423)




Elsa L Gunter  
2112 SC, UIUC

<http://www.cs.illinois.edu/class/cs423/>


Based on slides by Roy Campbell, Sam King, and  
Andrew S Tanenbaum

# Entry Layouts from Intel Manual





**Figure 3-14. Format of Page-Directory and Page-Table Entries for 4-KByte Pages and 32-Bit Physical Addresses**

# Translating 32 bit Virtual Address




# Translating 32 bit Virtual Address






# Translating 64 bit Virtual Address

Virtual (Linear) Address





# Translation Lookaside Buffer

---


- Problem: Accessing a memory location assoc with an instruction requires at least 3 memory accesses
  - Page directory entry
  - Page table entry
  - Info in memory location
- All instruction need at least 1, but up to three memory accesses
- Translates into 9 accesses IF all is currently in memory
- Answer: small cache of page table entries - TLB



# Page Deallocation

---

- Allocating memory fine so long as free memory exists
- Deallocating pages when process exits straightforward
- Problem: What to do when memory full of pages for active processes and more memory is needed?
- Answer: you have to pick something resident to kick out, but which one?



# Page Replacement Algorithms

---


- Optimal page replacement algorithm (fiction)
- Not recently used
- First In, First Out
- Second Chance
- Clock
- Least Recently Used
- Working Set
- Working Set Clock






# Second Chance Algorithm

- Start by storing pages FIFO




- When need to deallocate, if A has access bit set, reset bit and move A to new of FIFO




- Keep cycling; take first with access bit reset
  - May be A

# Clock Replacement Algorithm

- Modification of Second Chance
- Keep circular list, point to current candidate
- When page frame needed, inspect page pointed to
- If access bit reset, replace it
- If access bit set, reset and advance pointer





# Working Set Algorithm

---

- Observation: Locally processes only use small subset of their pages
- Set currently being used called **working set**
- Objective: reduce page fault rate by keeping working set in memory
- When process swapped out, pages replaced
  - Record pages present and recently referenced before replacing (working set)
- When process swapped in, **prepage** - replace old working set



# Working Set

---

- Definition: Virtual time  $t$  of process  $p$  is the amount of execution time (CPU time) of  $p$
- Definition: Working set of process  $p$  and  $k$  memory accesses at virtual time  $t$  is the number of  $p$ -pages referenced in the last  $k$  memory accesses before virtual time  $t$ 
  - Written  $w_p(k, t)$
  - $w_p(k, t) \leq w_p(k+n, t)$
- Hard to compute; replace mem access by virt time



# Working Set Algorithm

---

- Choose medium-sized  $k$ ; exact size not important
- At clock interrupt, all pages have reference bit reset
- At page fault, scan all (resident) pages
  - If Accessed bit set, record current virtual time ( $CVT$ ) as *time of last use (TLU)*
  - If Accessed bit reset, and  $TLU - CVT > k$ , evict
  - If Accessed bit reset, and  $TLU - CVT \leq k$ , keep looking
  - If no page with Accessed bit reset has  $TLU - CVT > k$ , evict oldest
  - If all pages have Accessed bit set, evict one randomly



# Working Set Clock

---

- Circular list of page info with *TLU*, *Accessed*, *Modified*
- At page fault, if page pointed to is *Accessed*, reset *Accessed* and move pointer ahead
- If not *Accessed* and age  $> k$ ,
  - Not *Modified*, then evict
  - *Modified*, then schedule write-to-disk, advance pointer
- If return to start
  - If write scheduled, keep going until one is clean
  - No write scheduled, evict random page