

# 12 Magnetic force and fields and Ampere's law

Pairs of wires carrying currents  $I$  running in the same (opposite) direction are known to attract (repel) one another. In this lecture we will explain the mechanism — the phenomenon is a relativistic<sup>1</sup> consequence of electrostatic charge interactions, but it is more commonly described in terms of magnetic fields. This will be our introduction to magnetic field effects in this course.

<sup>1</sup>**Brief summary of special relativity:** Observations indicate that light (EM) waves *can* be “counted” like particles and yet *travel* at one and the same speed  $c = 3 \times 10^8$  m/s in *all* reference frames in relative motion. As first recognized by Albert Einstein, these facts preclude the possibility that a *particle* velocity  $u$  could appear as

$$u' = u - v \quad (\text{Newtonian}) \quad \text{not for large velocities.}$$

to an observer approaching the particle with a velocity  $v$ ; instead,  $u$  must transform to the observer's frame as

$$u' = \frac{u - v}{1 - \frac{uv}{c^2}}, \quad (\text{relativistic}) \quad \text{relativistic velocity addition formula}$$

so that if  $u = c$ , then  $u' = c$  also. This “relativistic” velocity transformation in turn requires that positions  $x$  and times  $t$  of physical events transform (between the frames) as


$$x' = \gamma(x - vt) \quad \text{and} \quad t' = \gamma(t - \frac{v}{c^2}x), \quad (\text{relativistic})$$

where  $\gamma \equiv \frac{1}{\sqrt{1-v^2/c^2}}$ , rather than as  $u' = u - v$ .

$$x' = x - vt \quad \text{and} \quad t' = t, \quad (\text{Newtonian})$$

so that  $\frac{dx}{dt} = u$  and  $\frac{dx'}{dt'} = u'$  are related by the relativistic formula for  $u'$  given above.

Relativistic transformations imply a number of “counter-intuitive” effects ordinarily not noticed unless  $|v|$  is very close to  $c$ . One of them is Lorentz contraction, implied by  $dx = dx'/\gamma$  at a fixed  $t$ : since  $\gamma > 1$ ,  $dx < dx'$ , and moving objects having velocities  $v$  appear shorter than they are when viewed from other reference frames where  $v$  is determined. A second one is time dilation, implied by  $dt' = dt/\gamma$  at a fixed  $x'$ : since  $\gamma > 1$ ,  $dt' < dt$ , and moving clocks having velocities  $v$  and fixed  $x'$  run slower than clocks in other reference frames where  $v$  is determined. Consider taking PHYS 325 to learn more about special relativity.




“Things should be made as simple as possible – but no simpler.”


— Albert Einstein

- Consider a current carrying stationary wire in the lab frame:
  - the wire has a stationary lattice of positive ions,
  - electrons are moving to the left through the lattice with an average speed  $v$ , and
  - a current  $I > 0$  is flowing to the right as shown in the figure.
    - If the wire is electrically uncharged — which will be true if electron and ion charge densities in the wire,  $\lambda_- < 0$  and  $\lambda_+ > 0$ , respectively, have equal magnitudes — then the wire will produce no electrostatic field  $\mathbf{E}$ , and any stationary charge  $q$  placed near the wire will not be subject to any force<sup>2</sup>.
    - The current carried by the wire is  $I = v|\lambda_-| = v\lambda_+$  in terms of the magnitudes of electron velocity and charge density.
- An uncharged wire in the lab frame appears as “charged” in the reference frame of the electrons carrying the current:
  - this is a *relativistic effect* due to “Lorentz contraction” of the distances between the charges in the wire.

(a) Neutral wire carrying current  $I$  in the “lab frame”:



(b) In the “electron frame” the wire appears positively charged:



<sup>2</sup>This is true for zero-resistivity wires. Current carrying wires with *finite* resistivity will however support *surface* charge densities with axial gradients to produce the static field within the wire needed to drive the current — e.g., in *Am. J. Phys.*: Jefimenko, **30**, 19 (1962); Parker, **38**, 720 (1970); Preyer, **68**, 1002 (2000).

$$\lambda' \approx \lambda_+ \frac{v^2}{c^2} = \frac{Iv}{c^2} = Iv\mu_0\epsilon_0$$

- In the electron frame the wire is found to have a positive charge density  $\lambda'$ , and thus it has a radial electrostatic field

$$\checkmark \quad \mathbf{E}' = \frac{\lambda'}{2\pi\epsilon_0 r} \hat{r}$$

implying an electrostatic force  $\mathbf{F}' = q\mathbf{E}'$  on a stationary charge  $q$ .

- Relativistic calculations<sup>3</sup> show that

$$\checkmark \quad \lambda' \approx \lambda_+ \frac{v^2}{c^2} = \left(\frac{I}{v}\right) \frac{v^2}{c^2} = Iv\epsilon_0\mu_0$$

<sup>3</sup>(i) Electron spacings  $dx'$  measured in the electron reference frame will appear as

$$dx = \sqrt{1 - \frac{v^2}{c^2}} dx'$$

in the lab frame because of Lorentz contraction. Charge density of the electrons in the lab frame,

$$\lambda_- = \frac{\lambda'_-}{\sqrt{1 - v^2/c^2}},$$

is therefore greater in magnitude than the electron charge density  $\lambda'_-$  in the electron frame. Furthermore,  $\lambda_- = -\lambda_+$  in order to maintain a charge neutral wire in the lab frame. (ii) Once again because of Lorentz contraction, the charge density of positive ions will appear in the electron frame as

$$\lambda'_+ = \frac{\lambda_+}{\sqrt{1 - v^2/c^2}}.$$

(iii) Thus, the total charge density of the wire in the electron frame is


$$\lambda' = \lambda'_+ + \lambda'_- = \frac{\lambda_+}{\sqrt{1 - v^2/c^2}} + \lambda_- \sqrt{1 - v^2/c^2} = \frac{\lambda_+}{\sqrt{1 - v^2/c^2}} - \lambda_+ \sqrt{1 - v^2/c^2} = \frac{\lambda_+ v^2/c^2}{\sqrt{1 - v^2/c^2}} \approx \frac{\lambda_+ v^2}{c^2},$$

a *positive* density for non-zero  $|v| \ll c$ . (e.g., articles in *Am. J. Phys.*: Webster, **29**, 262, 1961; Matzek and Russel, **36**, 905, 1968; Arista and Lopez, **43**, 525, 1975; Zapolsky, **56**, 1137, 1988).


$$\lambda_+ = \frac{e}{\Delta x} = \frac{Ne}{L} = \frac{Ne v}{L v} = \frac{I}{v} \quad \text{A, } \frac{C}{s} \cdot \frac{s}{m} = \frac{C}{m}$$

$$N = \frac{L}{\Delta x} = \frac{I}{v} \quad \frac{C}{m}$$

(a) Neutral wire carrying current  $I$  in the "lab frame":



(b) In the "electron frame" the wire appears positively charged:



and force  $\mathbf{F}' = q\mathbf{E}'$  can be transformed back to the lab frame, where  $q$  appears to be moving with velocity  $\mathbf{v}$ , as (with no approximation<sup>4</sup>)

$$\mathbf{F} = q\mathbf{v} \times \frac{\mu_0 I}{2\pi r} \hat{\phi} \quad \mathbf{B}$$

where  $\hat{\phi}$  is the unit vector in the direction given by the *right-hand-rule* (see margin) and  $\mu_0 = 4\pi \times 10^{-7}$  H/m is *permeability* of free space.

- We find it convenient to define

$$\mathbf{B} \equiv \frac{\mu_0 I}{2\pi r} \hat{\phi} \rightarrow \mathbf{E} = \frac{\lambda}{2\pi\epsilon_0 r} \hat{r}$$

to be the “magnetic flux density” of current filament  $I$  at a distance  $r$ , and attribute the force

$$\mathbf{F} = q\mathbf{v} \times \mathbf{B}$$

on the moving charge  $q$  to the magnetic field  $\mathbf{B}$  produced by current  $I$  (rather than to the electrostatic field of the wire seen by  $q$  in its own reference frame).

While we assumed  $q$  to be stationary in the reference frame of the electrons in the above discussion (for the sake of simplicity), the results obtained above are found to be valid for all particle velocities  $\mathbf{v}$  measured in the lab frame.

<sup>4</sup>We also get the same result using the approximation  $\mathbf{F} = \mathbf{F}'$  that can be justified when  $|v| \ll c$ , which is typically true by a large margin for electron speeds in current carrying conducting metals — see HW.

(a) In the “electron frame” the wire appears positively charged and repels a test charge  $q$  with force  $\mathbf{F}' = q\mathbf{E}'$

$$\mathbf{F}' = q\mathbf{E}' = q \frac{\lambda'}{2\pi\epsilon_0 r} \hat{r} \approx qv \frac{\mu_0 I}{2\pi r} \hat{r}$$

$$\lambda' \approx \lambda_+ \frac{v^2}{c^2} = \frac{Iv}{c^2} = Iv\mu_0\epsilon_0$$

(b) In the lab frame force  $\mathbf{F} \sim \mathbf{F}'$  of moving charge  $q$  is attributed to magnetic field  $\mathbf{B}$  produced by current  $I$  and velocity  $\mathbf{v}$  of the charge in  $\mathbf{F} = q\mathbf{v} \times \mathbf{B}$  combination.

$$\mathbf{B} = \frac{\mu_0 I}{2\pi r} \hat{\phi}$$

Magnetic field  $\mathbf{B}$  curls around current  $I$  in a right-hand direction designated by unit vector  $\hat{\phi}$

Magnetic field lines close upon themselves unlike electric field lines which start and stop on point charges.

**Right hand rule:** point your right thumb in the direction of current flow; your fingers will point in direction  $\hat{\phi}$ .

Also, if there are multiple current filaments  $I_n$ , each generating its own field  $\mathbf{B}_n$ , force  $\mathbf{F}$  on  $q$  can be calculated using a superposition method as with electrostatic fields.

Magnetic field  $\mathbf{B}$  of the infinite current filament  $I$  obtained above can also be obtained by superposing the magnetic field increments

$$\underline{d\mathbf{B}} \equiv \frac{\mu_0 I d\mathbf{l} \times \hat{\mathbf{r}}}{4\pi r^2} \quad (\text{Biot-Savart law}) \quad \checkmark$$

of directed current increments  $\underline{Id\mathbf{l}}$ , where  $\mathbf{r} = r\hat{\mathbf{r}}$  is a position vector extending from the location of the current increment to the field position where  $d\mathbf{B}$  is being specified — this formula, known as Biot-Savart law, is only valid when used in terms of infinitesimal segments  $Id\mathbf{l}$  of time-invarying current loops.


- Magnetic field  $\mathbf{B}$  of the infinite line current  $I$  “derived” above satisfies a circulation relation

$$\oint_C \mathbf{B} \cdot d\mathbf{l} = \mu_0 I_C,$$



with  $I_C = I$ .

This integral for the circulation of static magnetic field  $\mathbf{B}$  is found to be valid (experimentally) for all closed circulation paths  $C$ , and is known as Ampere's law (for static magnetic fields). In Ampere's law

- $I_C$  stands for the net sum of all filament currents  $I_n$  crossing any surface  $S$  bounded by path  $C$ ,
  - flowing in the direction given by the “right-hand-rule”:



when the right thumb is pointed in the direction of  $d\mathbf{l}$  along path  $C$ , the direction of filament current  $I_n$  is specified as the direction of the fingers of your right hand through surface  $S$  bounded by contour  $C$ .



$$\oint \vec{H} \cdot d\vec{l} = I_c$$

- Ampere's law can also be expressed as

$$\oint_C \vec{H} \cdot d\vec{l} = \int_S \vec{J} \cdot d\vec{S}$$




where

- we have defined

$$\int_S \nabla \times \vec{H} \cdot d\vec{S}$$

$$\vec{H} \equiv \mu_0^{-1} \vec{B}$$

static. ✓




$$\vec{B} = \frac{\mu_0 I}{2\pi r} \hat{\phi}$$

$$\oint_C \vec{B} \cdot d\vec{l} = \mu_0 I_c$$

for the sake of convenience, and

- $\vec{J}$  is the volumetric current density measured in  $\text{A/m}^2$  units (e.g.,  $\sigma \vec{E}$  in a conducting region as discussed in last lecture) having a total flux

$$I_C = \int_S \vec{J} \cdot d\vec{S}$$



across any surface  $S$  bounded by a path  $C$ ,

- with  $d\vec{S}$  pointing across  $S$  in the direction compatible with right-hand-rule as in *Stoke's theorem* (recall Lecture 6).

- Stoke's theorem re-stated for a vector field  $\mathbf{H}$  as

$$\oint_C \mathbf{H} \cdot d\mathbf{l} = \int_S \nabla \times \mathbf{H} \cdot d\mathbf{S}$$

implies that the differential form of Ampere's law should be

$$\checkmark \nabla \times \mathbf{H} = \mathbf{J}.$$

This differential relation is accompanied by

$$\checkmark \nabla \cdot \mathbf{B} = 0, \quad \nabla \cdot \mathbf{B} = \cancel{\rho_m} = 0.$$

satisfied by static magnetic field of the line current *as well as* by any other magnetic field — static as well as non-static, as determined experimentally and described in more detail later on.

- Current density vector field  $\mathbf{J}$  invoked above in Ampere's law expressions, measured nominally in units of  $\text{A/m}^2$ , can also be adjusted to describe the distributions of surface or line currents in 3D space.

– For example,

$$\checkmark \mathbf{J}(x, y, z) = \mathbf{J}_s(y, z) \delta(x - x_0) \quad \swarrow \text{A/m}.$$

can be regarded as **volumetric current density** representation of a **surface current density**  $\mathbf{J}_s(x, y)$  measured in  $\text{A/m}$  units flowing on  $x = x_0$  surface.

$$\nabla \cdot \vec{D} = \rho. \quad \vec{B} = \mu_0 \vec{H}$$

$\uparrow \quad \uparrow$   
 $\text{H/m} \quad \text{A/m}.$   
 $\text{Wb/m}^2 \cdot \text{T}.$

Laws of magnetostatics:

$$\left\{ \begin{array}{l} \nabla \times \mathbf{H} = \mathbf{J} \\ \nabla \cdot \mathbf{B} = 0 \end{array} \right.$$

$\swarrow \quad \swarrow \quad \swarrow$   
 $\text{A/m} \quad \text{A/m} \quad \text{A/m}^2$   
 $\uparrow$   
 $\text{T}$

They also apply “quasi-statically” over a region of dimension  $L$  when a time-varying field source  $\mathbf{J}(\mathbf{r}, t)$  has a *time-constant*  $\tau$  much longer than the propagation time delay  $L/c$  of field variations across the region ( $c$  is the speed of light).

In magneto-quasistatics (MQS)  $\mathbf{B}(\mathbf{r}, t) = \mu_0 \mathbf{H}(\mathbf{r}, t)$  will be accompanied by a slowly varying electric field  $\mathbf{E}(\mathbf{r}, t)$  (derived from Faraday's law discussed in Lecture 14).

$$A \quad \text{⊗} \quad I. \quad J = I/A.$$



– Likewise,


$$\mathbf{J}(x, y, z) = \hat{z} I(z) \delta(x - x_o) \delta(y - y_o)$$

represents a **line current**  $I(z)$  measured in A units flowing in  $z$ -direction along a filament defined by the intersections of  $x = x_o$  and  $y = y_o$  surfaces.

– As a most extreme case,

$$\checkmark \mathbf{J}(x, y, z, t) = Q \mathbf{v} \delta(x - x_o) \delta(y - y_o) \delta(z - z_o)$$

represents the *time-varying* current density of a point charge  $Q$  at coordinates  $(x, y, z) = (x_o(t), y_o(t), z_o(t))$  moving with velocity  $\mathbf{v} = (\dot{x}_o(t), \dot{y}_o(t), \dot{z}_o(t))$ .



**Example 1:** Consider a surface current density of

$$\checkmark \mathbf{J}_s = \hat{z} y \text{rect}(y - 0.5) \text{ A/m}$$

flowing on  $x = 0$  plane (as shown in the margin). What is the total current  $I$  flowing on the same plane measured in A units?

**Solution:** To go from a surface current density  $\mathbf{J}_s$  in A/m to a total current  $I$  in A, we need to perform an appropriate integration operation on the surface where  $\mathbf{J}_s$  is defined. For the specified  $\mathbf{J}_s$  in this problem we find that

$$I = \int_{y=-\infty}^{\infty} \mathbf{J}_s \cdot \hat{z} dy = \int_{y=0}^1 y dy = \frac{y^2}{2} \Big|_0^1 = \frac{1}{2} \text{ A.}$$

$$\int_S \mathbf{J}_s \cdot d\vec{S}$$